

IUCLID 6 Desktop for Mac OS X

Publication date of this document: 15/11/2017

Version of this document: 1.2

1. System requirements

It is recommended to run *IUCLID 6 v2.0.0 for Mac OS X* on the latest version of OS X. Version 10.11.4 and later has been tested and shown to work. Some older versions do not work, for example, OS X Yosemite. The total RAM on the computer should be at least 4 GB.


IUCLID 6 Desktop and its associated software tools are Java applications and therefore require Java. The installer and the final installation of *IUCLID 6 Desktop for Mac OS X* both come with their own built-in installation of Java for Mac OS X. Therefore, the computer does not need to have a separate installation of Java.

2. Running the installer

The download package contains an installer in an [Apple Disk Image](#) with the file name:

```
iuclid6-installation-tool-<version>.dmg
```

Open the image by double-clicking on its icon. This opens a window and mounts the image so that it appears like a disk in the Finder, as shown below:




Launch the installer by double-clicking on the IUCLID 6 icon labelled `iuclid6-installer`.

After a few seconds a Java icon appears in the Dock and then the installer window opens. Follow the instructions in the installer. To install to a folder that differs from the default, click on the *Advanced* button, and then browse to the required folder. If you choose to use it, the migration from IUCLID 5 should work in the same way as it does for Windows.

3. Running IUCLID 6

The installation folder contains a Mac application file named `IUCLID6` which has the icon for *IUCLID 6 Desktop*. Dragging the icon to the Dock creates a link for starting the application, as shown below.



To start *IUCLID 6*, click on the icon in the Dock. During start-up, a splash screen is displayed. Once start-up is complete, by default, the homepage is shown. *IUCLID 6 Desktop for Mac OS X* is supplied by default with no log-in process and a single user, with username *SuperUser*. The first start-up can take several minutes. Subsequent start-ups are faster. Whilst *IUCLID 6 Desktop for Mac OS X* is starting up, two Java icons are shown in the Dock, but whilst it is running, only one is shown.

After *IUCLID 6 Desktop for Mac OS X* is shut down, the java icon disappears from the dock after a few seconds.


4. Updating IUCLID 6

IUCLID 6 Desktop for Mac OS X is updated using a Java application named *Updater tool*, which is available from the IUCLID 6 website. The *Updater tool* makes a backup automatically, but before updating, it is good practice to make a backup of the current version using the `Backup-Restore` tool that was supplied with the installation. After you have backed-up your data, shut down IUCLID 6 and then download the following package from the IUCLID 6 website:

```
iuclid6-desktop-updater-mac-<version>.dmg
```

```
iuclid_desktop_mac_en.docx
```

Open the image file by double-clicking on its icon. This opens a window and mounts the image so that it appears like a disk in the Finder, as shown below:



The interface of the *Updater tool*, is designed to be self-documenting. To start the *Updater tool*, double-click on its icon.